



New Jersey Department of Health and Senior Services

HAZARDOUS SUBSTANCE FACT SHEET

Common Name: **TRIPROPYL ALUMINUM**

CAS Number: 102-67-0

DOT Number: UN 3051

RTK Substance number: 1954

Date: March 1986

Revision: May 2000

HAZARD SUMMARY

- * **Trippropyl Aluminum** can affect you when breathed in.
- * Contact can severely irritate and burn the skin and eyes.
- * **Trippropyl Aluminum** is a **FLAMMABLE** and **REACTIVE** chemical and a **FIRE** and **EXPLOSION HAZARD**.

IDENTIFICATION

Trippropyl Aluminum is a thick, colorless liquid. It is used as a polyolefin catalyst.

REASON FOR CITATION

- * **Trippropyl Aluminum** is on the Hazardous Substance List because it is cited by ACGIH, DOT, NIOSH and NFPA.
- * This chemical is on the Special Health Hazard Substance List because it is **FLAMMABLE** and **REACTIVE**.
- * Definitions are provided on page 5.

HOW TO DETERMINE IF YOU ARE BEING EXPOSED

The New Jersey Right to Know Act requires most employers to label chemicals in the workplace and requires public employers to provide their employees with information and training concerning chemical hazards and controls. The federal OSHA Hazard Communication Standard, 1910.1200, requires private employers to provide similar training and information to their employees.

- * Exposure to hazardous substances should be routinely evaluated. This may include collecting personal and area air samples. You can obtain copies of sampling results from your employer. You have a legal right to this information under OSHA 1910.1020.
- * If you think you are experiencing any work-related health problems, see a doctor trained to recognize occupational diseases. Take this Fact Sheet with you.

WORKPLACE EXPOSURE LIMITS

The following exposure limits are for *Alkyl Aluminum compounds* (measured as *Aluminum*):

NIOSH: The recommended airborne exposure limit is **2 mg/m³** averaged over a 10-hour workshift.

ACGIH: The recommended airborne exposure limit is **2 mg/m³** averaged over an 8-hour workshift.

WAYS OF REDUCING EXPOSURE

- * Where possible, enclose operations and use local exhaust ventilation at the site of chemical release. If local exhaust ventilation or enclosure is not used, respirators should be worn.
- * Wear protective work clothing.
- * Wash thoroughly immediately after exposure to **Trippropyl Aluminum** and at the end of the workshift.
- * Post hazard and warning information in the work area. In addition, as part of an ongoing education and training effort, communicate all information on the health and safety hazards of **Trippropyl Aluminum** to potentially exposed workers.

This Fact Sheet is a summary source of information of all potential and most severe health hazards that may result from exposure. Duration of exposure, concentration of the substance and other factors will affect your susceptibility to any of the potential effects described below.

HEALTH HAZARD INFORMATION

Acute Health Effects

The following acute (short-term) health effects may occur immediately or shortly after exposure to **Tripropyl Aluminum**:

- * Contact can severely irritate and burn the skin and eyes.

Chronic Health Effects

The following chronic (long-term) health effects can occur at some time after exposure to **Tripropyl Aluminum** and can last for months or years:

Cancer Hazard

- * According to the information presently available to the New Jersey Department of Health and Senior Services, **Tripropyl Aluminum** has not been tested for its ability to cause cancer in animals.

Reproductive Hazard

- * According to the information presently available to the New Jersey Department of Health and Senior Services, **Tripropyl Aluminum** has not been tested for its ability to affect reproduction.

Other Long-Term Effects

- * **Tripropyl Aluminum** has not been tested for other chronic (long-term) health effects.

MEDICAL

Medical Testing

There is no special test for this chemical. However, if illness occurs or overexposure is suspected, medical attention is recommended.

Any evaluation should include a careful history of past and present symptoms with an exam. Medical tests that look for damage already done are not a substitute for controlling exposure.

Request copies of your medical testing. You have a legal right to this information under OSHA 1910.1020.

WORKPLACE CONTROLS AND PRACTICES

Unless a less toxic chemical can be substituted for a hazardous substance, **ENGINEERING CONTROLS** are the most effective way of reducing exposure. The best protection is to enclose operations and/or provide local exhaust ventilation at the site of chemical release. Isolating operations can also reduce exposure. Using respirators or protective equipment is less effective than the controls mentioned above, but is sometimes necessary.

In evaluating the controls present in your workplace, consider: (1) how hazardous the substance is, (2) how much of the substance is released into the workplace and (3) whether harmful skin or eye contact could occur. Special controls should be in place for highly toxic chemicals or when significant skin, eye, or breathing exposures are possible.

In addition, the following controls are recommended:

- * Where possible, automatically pump liquid **Tripropyl Aluminum** from drums or other storage containers to process containers.
- * All transfer lines must be free of water, *Oxygen* and other substances that react with **Tripropyl Aluminum**. All vessels must be dry and *Oxygen* free.
- * Transfer lines should be blanked when not in use. Vessels should be top unloading, when feasible, with remote manual pressure relief.
- * Before entering a confined space where **Tripropyl Aluminum** may be present, check to make sure that an explosive concentration does not exist.

Good **WORK PRACTICES** can help to reduce hazardous exposures. The following work practices are recommended:

- * Workers whose clothing has been contaminated by **Tripropyl Aluminum** should change into clean clothing promptly.
- * Contaminated work clothes should be laundered by individuals who have been informed of the hazards of exposure to **Tripropyl Aluminum**.
- * Eye wash fountains should be provided in the immediate work area for emergency use.
- * If there is the possibility of skin exposure, emergency shower facilities should be provided.
- * On skin contact with **Tripropyl Aluminum**, immediately wash or shower to remove the chemical. At the end of the workshift, wash any areas of the body that may have contacted **Tripropyl Aluminum**, whether or not known skin contact has occurred.
- * Do not eat, smoke, or drink where **Tripropyl Aluminum** is handled, processed, or stored, since the chemical can be swallowed. Wash hands carefully before eating, drinking, smoking, or using the toilet.

PERSONAL PROTECTIVE EQUIPMENT

WORKPLACE CONTROLS ARE BETTER THAN PERSONAL PROTECTIVE EQUIPMENT. However, for some jobs (such as outside work, confined space entry, jobs done only once in a while, or jobs done while workplace controls are being installed), personal protective equipment may be appropriate.

OSHA 1910.132 requires employers to determine the appropriate personal protective equipment for each hazard and to train employees on how and when to use protective equipment.

The following recommendations are only guidelines and may not apply to every situation.

Clothing

- * Avoid skin contact with **Trippropyl Aluminum**. Wear protective gloves and clothing. Safety equipment suppliers/ manufacturers can provide recommendations on the most protective glove/clothing material for your operation.
- * Exposure to large quantities, as in plant transfers, requires a full body aluminized proximity suit. Gloves used in plant transfers or operations should be *Aluminized Leather*, *Preformed Neoprene*, *Aluminized Vinyl* or other fire-resistant, nonreactive material. *Preformed Rubber* gloves may be used in the laboratory. All gloves used when handling *Aluminum Alkyls* should be loose-fitting for instant removal if necessary
- * All protective clothing (suits, gloves, footwear, headgear) should be clean, available each day, and put on before work.

Eye Protection

- * Wear indirect-vent, impact and splash resistant goggles when working with liquids.
- * Wear a face shield along with goggles when working with corrosive, highly irritating or toxic substances.

IMPROPER USE OF RESPIRATORS IS DANGEROUS.

Such equipment should only be used if the employer has a written program that takes into account workplace conditions, requirements for worker training, respirator fit testing and medical exams, as described in OSHA 1910.134.

- * Where the potential exists for exposure over **2 mg/m³**, use a MSHA/NIOSH approved supplied-air respirator with a full facepiece operated in a pressure-demand or other positive-pressure mode. For increased protection use in combination with an auxiliary self-contained breathing apparatus operated in a pressure-demand or other positive-pressure mode.

HANDLING AND STORAGE

- * Prior to working with **Trippropyl Aluminum** you should be trained on its proper handling and storage.
- * **Trippropyl Aluminum** is pyrophoric and will catch on fire if exposed to AIR.
- * **Trippropyl Aluminum** reacts violently with WATER to produce flammable and/or explosive gas.
- * **Trippropyl Aluminum** must be stored to avoid contact with OXYGEN; OXIDIZING AGENTS (such as PERCHLORATES, PEROXIDES, PERMANGANATES, CHLORATES, NITRATES, CHLORINE, BROMINE and FLUORINE); ALCOHOLS; CARBON TETRA-CHLORIDE; and CHLOROFORM since violent reactions occur.
- * Store in tightly closed containers in a cool, dry, well-ventilated area away from COMBUSTIBLE MATERIALS.
- * Sources of ignition, such as smoking and open flames, are prohibited where **Trippropyl Aluminum** is used, handled, or stored.
- * Metal containers involving the transfer of **Trippropyl Aluminum** should be grounded and bonded.
- * Use only non-sparking tools and equipment, especially when opening and closing containers of **Trippropyl Aluminum**.
- * Wherever **Trippropyl Aluminum** is used, handled, manufactured, or stored, use explosion-proof electrical equipment and fittings.

QUESTIONS AND ANSWERS

- Q: If I have acute health effects, will I later get chronic health effects?
- A: Not always. Most chronic (long-term) effects result from repeated exposures to a chemical.
- Q: Can I get long-term effects without ever having short-term effects?
- A: Yes, because long-term effects can occur from repeated exposures to a chemical at levels not high enough to make you immediately sick.
- Q: What are my chances of getting sick when I have been exposed to chemicals?
- A: The likelihood of becoming sick from chemicals is increased as the amount of exposure increases. This is determined by the length of time and the amount of material to which someone is exposed.
- Q: When are higher exposures more likely?
- A: Conditions which increase risk of exposure include physical and mechanical processes (heating, pouring, spraying, spills and evaporation from large surface areas such as open containers), and "confined space" exposures (working inside vats, reactors, boilers, small rooms, etc.).

- Q: Is the risk of getting sick higher for workers than for community residents?
- A: Yes. Exposures in the community, except possibly in cases of fires or spills, are usually much lower than those found in the workplace. However, people in the community may be exposed to contaminated water as well as to chemicals in the air over long periods. This may be a problem for children or people who are already ill.

The following information is available from:

New Jersey Department of Health and Senior Services
Occupational Health Service
PO Box 360
Trenton, NJ 08625-0360
(609) 984-1863
(609) 292-5677 (fax)

Web address: <http://www.state.nj.us/health/eoh/odisweb/>

Industrial Hygiene Information

Industrial hygienists are available to answer your questions regarding the control of chemical exposures using exhaust ventilation, special work practices, good housekeeping, good hygiene practices, and personal protective equipment including respirators. In addition, they can help to interpret the results of industrial hygiene survey data.

Medical Evaluation

If you think you are becoming sick because of exposure to chemicals at your workplace, you may call personnel at the Department of Health and Senior Services, Occupational Health Service, who can help you find the information you need.

Public Presentations

Presentations and educational programs on occupational health or the Right to Know Act can be organized for labor unions, trade associations and other groups.

Right to Know Information Resources

The Right to Know Infoline (609) 984-2202 can answer questions about the identity and potential health effects of chemicals, list of educational materials in occupational health, references used to prepare the Fact Sheets, preparation of the Right to Know survey, education and training programs, labeling requirements, and general information regarding the Right to Know Act. Violations of the law should be reported to (609) 984-2202.

DEFINITIONS

ACGIH is the American Conference of Governmental Industrial Hygienists. It recommends upper limits (called TLVs) for exposure to workplace chemicals.

A **carcinogen** is a substance that causes cancer.

The **CAS number** is assigned by the Chemical Abstracts Service to identify a specific chemical.

A **combustible** substance is a solid, liquid or gas that will burn.

A **corrosive** substance is a gas, liquid or solid that causes irreversible damage to human tissue or containers.

DEP is the New Jersey Department of Environmental Protection.

DOT is the Department of Transportation, the federal agency that regulates the transportation of chemicals.

EPA is the Environmental Protection Agency, the federal agency responsible for regulating environmental hazards.

A **fetus** is an unborn human or animal.

A **flammable** substance is a solid, liquid, vapor or gas that will ignite easily and burn rapidly.

The **flash point** is the temperature at which a liquid or solid gives off vapor that can form a flammable mixture with air.

HHAG is the Human Health Assessment Group of the federal EPA.

IARC is the International Agency for Research on Cancer, a scientific group that classifies chemicals according to their cancer-causing potential.

A **miscible** substance is a liquid or gas that will evenly dissolve in another.

mg/m³ means milligrams of a chemical in a cubic meter of air. It is a measure of concentration (weight/volume).

MSHA is the Mine Safety and Health Administration, the federal agency that regulates mining. It also evaluates and approves respirators.

A **mutagen** is a substance that causes mutations. A **mutation** is a change in the genetic material in a body cell. Mutations can lead to birth defects, miscarriages, or cancer.

NAERG is the North American Emergency Response Guidebook. It was jointly developed by Transport Canada, the United States Department of Transportation and the Secretariat of Communications and Transportation of Mexico. It is a guide for first responders to quickly identify the specific or generic hazards of material involved in a transportation incident, and to protect themselves and the general public during the initial response phase of the incident.

NCI is the National Cancer Institute, a federal agency that determines the cancer-causing potential of chemicals.

NFPA is the National Fire Protection Association. It classifies substances according to their fire and explosion hazard.

NIOSH is the National Institute for Occupational Safety and Health. It tests equipment, evaluates and approves respirators, conducts studies of workplace hazards, and proposes standards to OSHA.

NTP is the National Toxicology Program which tests chemicals and reviews evidence for cancer.

OSHA is the Occupational Safety and Health Administration, which adopts and enforces health and safety standards.

PEOSHA is the Public Employees Occupational Safety and Health Act, a state law which sets PELs for New Jersey public employees.

ppm means parts of a substance per million parts of air. It is a measure of concentration by volume in air.

A **reactive** substance is a solid, liquid or gas that releases energy under certain conditions.

A **teratogen** is a substance that causes birth defects by damaging the fetus.

TLV is the Threshold Limit Value, the workplace exposure limit recommended by ACGIH.

The **vapor pressure** is a measure of how readily a liquid or a solid mixes with air at its surface. A higher vapor pressure indicates a higher concentration of the substance in air and therefore increases the likelihood of breathing it in.

